

| Vibes | - Analog



Vibes - A


Mobile App User Guide

Read the user's manual carefully before starting to use the unit or software.

Producer reserves the right to implement changes without prior notice.


Step - 1 Instructions

✓ Open Vibes configurator app on your Android device. Turn OFF the sensor device and Turn ON the configurator device to pair with the sensor device.



Step - 2 Device Connection

✓ Connect your mobile wi-fi with Vibes device and return to the Vibes configuration app and select configure.




Connect your device to 'Vibes-xxxxxx' and return to the Vibes configuration app Default Password: password




Step - 3 Dashboard

✓ Here you can monitor device data on local dashboard



Step - 4 Wi-Fi & Server Configuration


Enter your device SSID credentials & server credentials in Wi-fi credentials to view sensor data on cloud server.





Step - 5 Configuration for Modbus Devices

Enter Modbus device ID and Baud Rate (only for MODBUS Devices)




Step - 6 Data Logger Configuration

Settings

- 1. Todays Date & Time
- 2. Logging Interval required (Minimum 1 Minute Interval)

Data Management

- 1. Download file by clicking the download button in CSV format
- 2. A new file will be generated in mm/yy format every calender month
- 3. Delete files after downloading as per your choice. Please note file will be deleted permanently



Step - 7 Sensor Configuration

Enter your sensor data. Ensure the details you have entered are visible in "Current Stored Values".

Analog Settings

